


# How to setup L2TP VPN Dialer for Windows 7




# How to setup L2TP VPN Dialer for Windows 7

Setting up VPN Dialer access under Windows 7 is simple. Follow the instructions that define a step-by-step procedure that will lead you through the creation process of a L2TP/IPsec VPN connection.

## Open Network Connections

1. First, go to the Start Menu and select Control Panel.



2. Click on the “Network and Internet” control panel, which is circled below in red.



3. Click on “View network status and tasks.”




## Set up a connection

4. Then click on “Set up a new connection or network”.




The “Set up a new connection or network” window will now be displayed.

5. Click on “Connect to a workplace”, and then click “Next” in the lower right hand section of the window.




## How do you want to connect?

6. Next, you will be asked how do you want to connect. Click on “Use my Internet connection.(VPN)”




## Set up the Internet Address

7. On this screen, type the name and IP address of the VPN server, and click Next.



## Fill in your username and password


8. Type in your VPN username and password. Check the “Remember this password” box.



9. Click on “Connect”. If you see the message, “You are connected” it means you have successfully set up the VPN connection.

## Connection Ready

10. You should see the following screen next. Click the “Close” button to return to the “Network and Internet” screen.




11. In the “Connect to a network” screen, you should see the VPN connection that you have just set up.



12. Right click on the VPN connection document, and choose "Properties" from the menu.




13. In the VPN properties, click on the type of VPN pop-up menu (highlighted in red) and select L2TP/IPsec.



14. Next, click on the “Advanced Settings” button. (highlighted in red)



In the IPsec Settings dialog, click on the radio button labelled, “Use preshared key for authentication” (highlighted in green). Then type hideipvpn into the text-box labelled **Key**. Then click the OK button



Click the OK button to save your settings.

### **Connect To HideIPVPN (Firewall IP as specified)**

When you want to connect to hideipvpn.com, just double-click on the connection and click on the Connect button. Enter your username and password (if you didn't save it), and you'll connect.

### **Disconnect From HideIPVPN (Firewall IP as specified)**

To disconnect from a VPN connection, right-click the icon for the connection, and then click Disconnect.

You have successfully set up L2TP VPN Dialer for Windows 7